

Ferti-SprayMate™

ON-FARM MIXES GET A BETTER RESULT!



Five in One – Chelator, Sticker, Wetter, pH Adjuster and Buffer.

Powerful Fulvic Acid based D.I.Y spray additive with NIOSS (non-ionic organo-silicon surfactants) and all the other pH control and foliar chemistry features needed for the most effective spraying results.

Rainfast after 1 hour, Ferti-SprayMate™ is a low cost but highly effective fertiliser adjuvant with natural chelators. Fast penetrating with a very Leaf Friendly chemical construction to maximise Phloem Penetration, Ferti-SprayMate™ also contains humic and fulvic acids (15% Bio-Fulvic solution w/v) to aid chelation, respiration, photo-sensitivity and nutrient transfer. Use Ferti-SprayMate™ to ensure your “Farm-Made” foliar is made to do a better job - more targeted, effective and complete.

Application

- **0.5-1% addition to Spray Cart.** Do not use less by volume. Ensure the most effective sticking and wetting properties are achieved. (eg: 1000L Water = 5-10 litres Ferti-SprayMate™)
- 1% addition to Spray Cart with High Calcium, High Alkaline, Heavily Mineralised Bore Water (eg: 1000L Water = 10 litres Ferti-SprayMate™)

Preparation

- Fill Cart with Water, Then Add Ferti-SprayMate™, then agitate, then add Mix. Jar Test of proposed Cart Mix always recommended before Use. Do not Spray under 50 litres Cart Mix (Water / Ferti-SprayMate / Target Foliar Addition) per Hectare



Ferti-Tech are the Leaders in Carbon Systems Agronomy Research and Manufacturing of Strategic Foliar Applications.

Our formulations have proven Yield Responses and we can help your mixes too.



Sulphates – Oxides – Micronised Particulates STILL NEED TO BOND, STICK & PENETRATE

Ferti-SprayMate™ will adjust Cart Water, Foliar pH and prepare Cart Water for Optimal Foliar Use. Fulvic, Amino and other Organic Acids aid Chelation. Non-Ionic Organo-Silicone Surfactants and other modified additives are used to ensure sticking and wetting ability.

5 Jobs for \$1-\$2 per Ha.

On-Farm Foliar Mixing

Can always be improved with **Ferti-SprayMate™**.
Formulations can always be given extra penetrating power.
Effective – Works – Cheap



Caution Ferti-SprayMate™

Not Suitable for Use with High (10+ w/v) Phosphorus Mixes or where any SOIL-BASED RESIDUAL Effects are Desired.

Ferti-Tech Carbon Systems Agronomy

(08) 9725 6877 PO Box 9129 PICTON WA 6230 www.fertitech.com info@fertitech.com